

NOW **START-UP KIT**

Version 2.0

Should you have any queries we will be happy to help.
Please call to speak to NOW Team
Website – www.nowonline.in

<p>Regards NOW Team 1800 22 0052 (Toll Free) e-mail : now@nse.co.in</p>	<p>MAKE THE MOST OF NOW  POWER IN YOUR HANDS</p>
--	--



Table of content

1. System Configuration	2
2. Installation procedure for 'NOW.Exe'	4
3. Login procedure for Internet clients	4
4. User Manual	4



1. System Configuration

a. For Admin / Dealer - EXE

- Intel(R) Core(TM) 2 Duo Processor
- Minimum 1GB RAM
- Minimum 80GB Hard Drive.
- Operating System: Microsoft(R) Windows XP Professional SP2 with latest windows updates.
- Minimum Internet Bandwidth 512Kbps

b. Opening of Ports for 'EXE'

Ensure that ports are open in firewall at your end or contact your Internet service provider (ISP) for the opening of following ports under domain name:

- 1st Domain Name = neatonweb.com (125.17.127.71)
 - Port Require to get Login = 56000, 64102
 - 35000, 35001, 35002, 35003, 35004, 35005, 35006, 35007, 35008, 35009, 35010.
 - 2nd Domain Name = nse-now.com (125.17.127.72)
 - Port Require to get Login = 65000, 56000
 - 35000, 35001, 35002, 35003, 35004, 35005, 35006, 35007, 35008, 35009, 35010.
 - Additional IP required to be entered in firewall - 125.17.127.79 to 96
 - Port required to be opened - 35000, 35001, 35002, 35003, 35004, 35005, 35006, 35007, 35008, 35009, 35010.
 - Telnet the ports to check whether its is opened:
 - Go to Start – Run – type CMD
 - Command Prompt will open
 - Check following commands
- For 1st Domain Name:
- telnet neatonweb.com 56000
 - telnet neatonweb.com 64102
- Check ports from below mentioned list is opened:
- telnet neatonweb.com 35000
 - telnet neatonweb.com 35001
 - telnet neatonweb.com 35002
 - telnet neatonweb.com 35003
 - telnet neatonweb.com 35004
 - telnet neatonweb.com 35005, etc.



For 2nd Domain Name:

- telnet nse-now.com 56000
- telnet nse-now.com 65000

Check ports from below mentioned list is opened:

- telnet nse-now.com 35000
 - telnet nse-now.com 35001
 - telnet nse-now.com 35002
 - telnet nse-now.com 35003
 - telnet nse-now.com 35004
 - telnet nse-now.com 35005, etc.
- If the port is opened the command prompt screen will remain blank otherwise it will display 'Connect Failed' port is not open for domain name.

c. For Internet client - Browser

- Intel(R) Core(TM) 2 Duo Processor
- Minimum 512MB RAM
- Internet Explorer 5.0 and above with Java Enabled
- JAVA plug-in for viewing chart, streaming quotes and instant alerts on web page
- JRE version 6 update 11
- Enable cookies on your web browser.
- For firewall or proxy server, enable ports 443 and 80 for streaming quotes and alerts
- Minimum Internet Bandwidth 256Kbps



2. Installation procedure for 'NOW.Exe'

- Go to Extranet FTP server (IP - 203.199.75.110)
- Enter your username and password as provided by exchange
- Go to Extranet in following folder to download setup
 - For CM Segment: /Common/NOW/Setup
 - For FO Segment: /faocommon/NOW/Setup
 - For CD Segment: /cdscommon/NOW/Setup
- Download 'NOW Setup.zip' file to your desktop.
- Extract 'NOW.exe' to your desktop. Double click on 'NOW.exe' icon to install it.
- The exe is installed at 'C:\Program Files\NOW'.
- To run the application:
 - Click on 'Launch NOW' icon placed on your desktop, or
 - Go to 'Start – Program – Dotex International – NOW – Launch NOW.exe'.

3. Login procedure for Internet clients

- Contact your member for Member ID, User ID and password.
- The above details will be received through your mail ID, as provided to your member.
- Login to 'www.nowonline.in' or 'www.now-online.in'.
- Enter your Member ID, User ID and password as provided.

4. User Manual

For detailed information and procedural steps for using the NOW application, you are requested to view each module as follows kept in FTP-common/NOW/Manual folder:

- NOW info handbook
- Admin functionality
- Risk management functionality
- Dealer functionality
- Internet client functionality

BLANK PAGE